

## **ENTERPRISE ARCHITECT**

**User Guide Series** 

# **Model Transformation**

Author: Sparx Systems

Date: 10/11/2023

Version: 16.1



## **Table of Contents**

Model Transformation	3
Transform Elements	6
Chaining Transformations	
Built-in Transformations	g
C# Transformation	11
C++ Transformation	13
Data Model To ERD Transformation	
DDL Transformation	
EJB Transformations	20
ERD To Data Model Transformation	23
Java Transformation	26
JUnit Transformation	
NUnit Transformation	30
PHP Transformation	32
Sequence/Communication Diagram Transformations	33
VB.Net Transformation	
WSDL Transformation	36
XSD Transformation	
Edit Transformation Templates	41
Write Transformations	
Default Transformation Templates	45
Intermediary Language	46
Intermediary Language Debugging	
Objects	
Connectors	
Transform Connectors	58
Transform Foreign Keys	60
Copy Information	
Convert Types	
Convert Names	63
Cross References	65
Transform Template Parameter Substitution	66

## **Model Transformation**

One of the great advantages of creating models is the ability to manipulate them to produce outputs, thus saving time and reducing the possibility of errors. Enterprise Architect implements Model Driven Architecture (MDA) transformations using a flexible and fully configurable template system. The templates act as instructions to a machine that takes a model as input and transforms it to a more resolved model as output. The input could be a large and complex model or a single element and one input model could be transformed to a variety of output models.

The transformations are commonly unidirectional and take a Platform Independent Model (PIM) and transform it to one or more Platform Specific Models (PSM). A good example of where this is useful is where a system must be implemented in a number of different relational database systems. A single platform independent conceptual model (the PIM) could be transformed to a number of platform specific models, say Oracle, MySQL and SQLite. As a further productivity boost, once the output models are produced they can also be converted to programming code, database definition language or schemas. Enterprise Architect automatically creates traceability that can be used to visualize how elements in the input model have been transformed to elements in the output model.

#### **Facilities**

Facility	Description
Transform Elements	Discover how to transform elements on a diagram or from a Browser window Package.
Built-in Transformations	Enterprise Architect provides a number of built-in transformations that support a wide range of target languages. Each is fully customizable to your specific needs.
Edit Transformation Templates	Learn how to adjust the transformation templates to produce transformations specific to your system.
Write Transformations	All the information you will need to create your own transformations.

### **Ready-built Transformations**

The Enterprise Architect installer includes a number of basic built-in transformations, including:

- PIM to:
  - C#
  - C++
  - DDL table elements
  - EJB Entity Bean

- EJB Session Bean
- Java
- PHP
- VB.Net
- XSD
- Data Model to Entity Relationship diagram (ERD)
- Entity Relationship diagram (ERD) to Data Model
- Sequence diagram to Communication diagram
- Communication diagram to Sequence diagram
- Java model to JUnit test model
- .NET model to NUnit test model
- WSDL interface model to WSDL

Further transformations will become available over time, either built in or as downloadable modules from the Sparx Systems website.

#### **Customized Transformations**

You can modify the built-in transformations or define your own, using Enterprise Architect's simple code generation template language. This involves little more than writing templates to create a simple intermediary source file; the system reads the source file and binds that to the new PSM.

### **Transformation Dependencies**


When you execute a transformation, the system creates internal bindings (Transformation Dependencies) between each PSM created and the original PIM. This is essential, providing the ability to forward synchronize from the PIM to the PSM many times, adding or deleting features as you go; for example, adding a new attribute to a PIM Class can be forward synchronized to a new column in the Data Model.

You can observe the Transformation Dependencies for a Package using the Traceability window, to check the impact of changes to a PIM element on the corresponding elements in each generated PSM, or to verify where a change required in a PSM should be initiated in the PIM (and also to reflect back in other PSMs). The Transformation Dependencies are a valuable tool in managing the traceability of your models.

Enterprise Architect does not delete or overwrite any element features that were not originally generated by the transform; therefore, you can add new methods to your elements, and Enterprise Architect does not act on them during the forward generation process.

### **Example of a Transformation**

This diagram highlights how transformations work and how they can significantly boost your productivity.



#### **Notes**

• If you are using the Corporate, Unified or Ultimate Edition, if security is enabled you must have 'Transform Package' access permission to perform an MDA Transformation on the elements of a Package

## **Transform Elements**

A model transformation is a user initiated function that starts the process of transforming one or more Platform Independent Model (PIM) elements into their corresponding Platform Specific Model (PSM) elements. This process takes place in accordance with the rules that have been codified in the Transformation Templates. The transformation can be initiated by selecting a Package in the Browser window or an element in a diagram.

#### **Access**

Ribbon	Design > Package > Transform > Transform Selection
Keyboard Shortcuts	Ctrl+H (transform selected elements) Ctrl+Shift+H (transform selected Package)

### **Perform a Transformation**

Option	Action
Elements	Lists all of the individual elements selected in the diagram or held in the Package. Either:
	Click on an element to include just that element in the transformation
	<ul> <li>Hold Ctrl and click on several separate elements to include them in the transformation, or</li> </ul>
	Hold Shift and click on the first and last elements in a block to include those elements in the transformation
All	Click on this button to select all of the elements in the list to include them in the transformation.
None	Click on this button to deselect all of the elements in the list.
Include child packages	(If you have selected to transform elements in a Package.)
	Select this checkbox to include (in the 'Elements' list and potentially in the transformation) elements from the child Packages of the selected Package.
Transformations	Select the checkbox against each type of transformation to perform. When you select a checkbox, the 'Browse Project' dialog displays; locate and select the target Package into which to generate the transformed elements.
	If you want to change a selected target Package, click on the button to the right of the Package name and select the new Package from the dialog.
Generate Code on result	Select this checkbox to specify whether or not to automatically generate code for transformed Classes that target code languages.
	If you select this option, the first time you transform to the Class the system prompts you to select a filename to generate code into; subsequent transformations

	automatically generate code to that filename.
Perform Transformations on result	Select the checkbox to automatically execute transformations previously done on the target Class or Classes.
Intermediary File	If you want to capture the intermediary language file (for example, to debug it), either type in the file path and name or click on the button and locate and select the file.
Write Always	Select this checkbox to always write the intermediary file to disk.
Write Now	Click on this button to generate the intermediary file without performing the full transformation.
Do Transform	Click on this button to execute the transformation.  When the transformation is complete, the 'Model Transformation' dialog closes.
Close	Click on this button to close the 'Model Transformation' dialog without performing the transformation.

### **Notes**

- When the dialog displays, all elements are selected and all transformations previously performed from any of these Classes are checked
- This procedure does not apply to the Sequence diagram/Communication diagram transformation, or the Communication diagram/Sequence diagram transformation

## **Chaining Transformations**

Chaining transformations provides an extra degree of flexibility and power to performing transformations. For example, if two transformations have a common element; you might separate this element out into its own transformation, and then perform the original transformations from the common point. The separated transform could even produce a useful model itself.

You can chain transformations by selecting the 'Perform Transformations on result' checkbox in the 'Model Transformation' dialog, so that transformations that have already been performed on target Classes are executed automatically next time that Class is transformed to.

## **Built-in Transformations**

Enterprise Architect provides a rich set of built-in, commonly performed transformations. These will prove useful to a variety of disciplines from Domain Modeling to Code Engineering. The facility to transform models is a practical productivity tool and it is expected that modelers will want to create their own custom transformations. The built-in transformations provide useful examples and are a valuable reference for the modeler.

#### **Built-in Transformations**


Transformation	Converts
C#	Platform-Independent Model (PIM) elements to language-specific C# Class elements.
C++	PIM elements to language-specific C++ Class elements.
Data Definition Language	A logical model to a data model targeted at the default database type, ready for DDL generation.
Entity Relationship Diagram to Data Model	An ERD logical model to a data model targeted at the default database type, ready for DDL generation.
Data Model to Entity Relationship Diagram	A data model to an ERD logical model.
EJB Session Bean	A single Class element to the elements of an EJB session.
EJB Entity Bean	A single Class element to the elements of an EJB entity.
Java	PIM elements to language-specific Java Class elements.
JUnit	An existing Java Class element with public methods to a Class with a test method for each public method, plus the methods required to appropriately set up the tests.
NUnit	An existing .NET compatible Class with public methods to a Class with a test method for each public method, plus the methods required to appropriately set up the tests.
PHP	PIM elements to language-specific PHP Class elements.
Sequence/Communication Diagram	All elements and messages in an opened Sequence diagram into matching elements and messages in a Communication diagram, and vice versa.
VB.Net	PIM elements to language-specific VB.Net Class elements.
WSDL	A simple model to an expanded model of a WSDL interface, suitable for generation.
XSD	PIM elements to UML Profile for XML elements, as an intermediary step in creating an XML Schema.


## **C# Transformation**

The C# transformation converts Platform-Independent Model (PIM) element types to C#-specific Class element types, and creates encapsulation according to the system options you have set for creating properties from C# attributes (on the 'C# Specifications' page of the 'Preferences' dialog).

### **Example**

#### The PIM elements






## **C++ Transformation**

The C++ transformation converts Platform-Independent Model (PIM) element types to C++ specific Class element types and creates encapsulation (producing the getters and setters) according to the options you have set for creating properties from C++ attributes (on the 'C++ Specifications' page of the 'Preferences' dialog). Note that the public attributes in the PIM are converted to private attributes in the PSM. All operations on an interface are transformed into pure virtual methods on an equivalent class.

### **Example**

The PIM elements





## **Data Model To ERD Transformation**

The Data Model to Entity Relationship diagram (ERD) transformation creates an ERD logical model from a Data Model. It is the reverse of the ERD to Data Model transformation. This transformation uses and demonstrates support in the intermediary language for a number of database-specific concepts.

### **Supported Concepts**

Concept	Effect
Entity	Mapped one-to-one onto Table elements.
Attribute	Mapped one-to-one onto Columns.
Primary Key	Derived from the PrimaryKey type of column.

#### **Notes**

• Sometimes you might want to limit the stretch of the diamond-shaped Relationship connectors; simply pick a Relationship connector, right-click to display the context menu, and select the 'Bend Line at Cursor' option

## **DDL Transformation**

The DDL transformation converts the logical model to a data model structured to conform to one of the supported DBMSs. The target database type is determined by which DBMS is set as the default database in the model (see the *Database Datatypes* Help topic, 'Set As Default' option). The data model can then be used to automatically generate DDL statements to run in one of the system-supported database products.

The DDL transformation uses and demonstrates support in the intermediary language for a number of database-specific concepts.

### **Concepts**

Concept	Effect
Table	Mapped one-to-one onto Class elements.  'Many-to-many' relationships are supported by the transformation, creating Join tables.
Column	Mapped one-to-one onto attributes.
Primary Key	Lists all the columns involved so that they exist in the Class, and creates a Primary Key Method for them.
Foreign Key	A special sort of connector, in which the Source and Target sections list all of the columns involved so that:
	The columns exist
	A matching Primary Key exists in the destination Class, and
	The transformation creates the appropriate Foreign Key

### MDG Technology to customize default mappings

DDL transformations that target a new, user defined DBMS require an MDG Technology to map the PIM data types to the new target DBMS.

To do this, create an MDG Technology .xml file named 'UserDBMS Types.xml', replacing UserDBMS with the name of the added DBMS. Place the file in the EA\MDGTechnologies folder. The contents of the MDG Technology file should have this structure:


As an example, 'text' is a Common Type (as listed in the 'Database Datatypes' dialog) that maps to a new DBMS's 'CLOB' data type.


#### **Notes**

• You can define DBMS-specific aspects not depicted in a Logical model, such as Stored Procedures, Triggers, Views and Check Constraints, after the transformation; see the *Physical Data Model* Help topic


### **Example**

The PIM elements





Generalizations are handled by providing the child element with a Foreign Key to the parent element, as shown. Copy-down inheritance is not supported.



## **EJB Transformations**

The EJB Session Bean and EJB Entity Bean transformations reduce the work required to generate the internals of Enterprise Java Beans. You can therefore focus on modeling at a higher level of abstraction.


### **Transformations**

Both transformations also generate a META-INF Package containing a deployment descriptor element.


Transformation	Detail
EJB Session Bean	This transformation converts a single Class element (containing the attributes, operations and references required for code generation by the javax.ejb.* Package) to  • An implementation Class element
	A home interface element
	A remote interface element
EJB Entity Bean	This transformation converts a single Class element (containing the attributes, operations and references required for code generation by the javax.ejb.* Package) to:
	An implementation Class element
	A home interface element
	A remote interface element
	A Primary Key element

### **Example**

The PIM elements



After transformation generate a set of Entity Beans, where each one takes this form (for the Account Class):



## **ERD To Data Model Transformation**

The Entity Relationship Diagram (ERD) to Data Model transformation converts an ERD logical model to a data model targeted at the default database type, ready for generating DDL statements to run in one of the system-supported database products. Before doing the transformation, you define the common data type for each attribute and select a database type as the default database. You can then automatically generate the Data Modeling diagram.

The transformation uses and demonstrates support in the intermediary language for a number of database-specific concepts.

### **Concepts**


Concept	Definition
Table	Mapped one-to-one onto Class elements.
Column	Mapped one-to-one onto attributes.
Primary Key	Lists all the columns involved so that they exist in the Class, and creates a Primary Key Method for them.
Foreign Key	A special sort of connector, in which the Source and Target sections list all of the columns involved so that:
	• The columns exist
	A matching Primary Key exists in the destination Class, and
	The transformation creates the appropriate Foreign Key

#### Generalization


ERD technology can handle Generalization, as shown. Note that the copy-down inheritance is currently supported with two levels only.

### **Example**

The ERD elements



After transformation, become the Data Model elements



### **Notes**





## **Java Transformation**

The Java transformation converts Platform-Independent Model (PIM) element types to Java-specific Class element types, and creates encapsulation (producing the getters and setters) according to the options you have set for creating properties from Java attributes (on the 'Java Specifications' page of the 'Preferences' dialog). Note that the public attributes in the PIM are converted to private attributes in the PSM. All operations in the interface are transformed into pure virtual methods.

### **Example**

The PIM elements







## **JUnit Transformation**

The JUnit transformation converts an existing Java Class with public methods into a Class with a test method for each public method. The resulting Class can then be generated and the tests filled out and run by JUnit.

### **Example**

The Java model elements (originally transformed from the PIM)





#### **Notes**


For each Class in the Java model, a corresponding Test Class has been created containing a test method for every
public method in the source Class, plus the methods required to appropriately set up the tests; you fill in the details
of each test


## **NUnit Transformation**

The NUnit transformation converts an existing .NET compatible Class with public methods into a Class with a test method for each public method. The resulting Class can then be generated and the tests filled out and run by NUnit.

### **Example**

The C# elements (originally transformed from the PIM)





#### **Notes**

• For each Class in the C# model, a corresponding Test Class has been created containing a test method for every public method in the source Class, plus the methods required to appropriately set up the tests; you fill in the details of each test


## **PHP Transformation**

The PHP transformation converts Platform-Independent Model (PIM) element types to language-specific PHP Class element types and creates encapsulation (producing the getters and setters) according to the options you have set for creating properties from PHP attributes (on the 'PHP Specifications' page of the 'Preferences' dialog). Note that the public attributes in the PIM are converted to private attributes in the PSM.

### **Example**

The PIM elements





## **Sequence/Communication Diagram Transformations**

Sequence diagrams can be transformed into a Communication diagram, and Communication diagrams into a Sequence diagrams. In each case, every element or message in the source diagram type is mapped 1:1 to a matching element or message in the target diagram.

#### **Access**

Ribbon	Design > Package > Transform > Transform Selection
Keyboard Shortcuts	Ctrl+Shift+H (transform current Package) Ctrl+H (transform selected elements)

### **Perform a Transformation**

The diagram being transformed must be open in the main diagram view for the 'Communication' or 'Sequence' options to appear in the Model Transformation dialog.

Step	Action
1.	Open and select in the diagram view, the diagram to be transformed.
2.	Open the <i>Model Transform</i> dialog using:
	Design > Package > Transform > Transform Selection (Ctrl+Shift+H).
3.	In the <i>Elements</i> list, highlight all the elements from the diagram, which will be included in the transformation.
4.	In the <i>Transformations</i> list, select:
	The 'Communication' checkbox, if transforming a Sequence diagram into a Communication diagram, or
	The 'Sequence' checkbox, if transforming a Communication diagram into a Sequence diagram
	The 'Browse Project' dialog displays.
	Browse for and select the target Package into which the target diagram will be created, then click on the $OK$ button.
5.	Click on the <i>Do Transform</i> button to execute the transformation.
	The target diagram is created and listed in the Browser window under the target Package with the name (depending on which transformation you have executed):
	<source diagram="" name=""/> Communication or
	<source diagram="" name=""/> Sequence

### **Notes**

Once you have selected the 'Communication' or 'Sequence' checkbox, these transforms ignore any other field setting
in the dialog except for 'Target Package', and will perform a direct transformation of every element in the source
diagram


## **VB.Net Transformation**

The VB.Net transformation converts Platform-Independent Model (PIM) element types to language-specific VB.Net Class element types, and creates encapsulation according to the options you have set for creating properties from VB.Net attributes (on the 'VB.Net Specifications' page of the 'Preferences' dialog). Note that the public attributes in the PIM are converted to private attributes in the PSM.

### **Example**

The PIM elements






## **WSDL Transformation**

The WSDL transformation converts a simple model into an expanded model of a WSDL interface that is suitable for generation. For example:



Transformation of this generates the corresponding WSDL Component, Service, Port Type, Binding and Messages:

- Classes are handled in the same way as in the XSD Transformation
- All 'in' parameters are transformed into WSDL Message Parts in the Request message
- The return value and all 'out' and 'return' parameters are transformed into WSDL Message Parts in the Response message
- All methods where a value is returned are transformed into Request-Response operations, and all methods not returning a value are transformed into OneWay operations
- The transformation does not handle the generation of Solicit-Response and Notification methods or faults




In the resulting Package you can then fill out the specifics using the WSDL editing capabilities of Enterprise Architect, and finally generate the Package using the WSDL generation tools.

## **XSD Transformation**


The XSD transformation converts Platform-Independent Model (PIM) elements to UML Profile for XML elements as an intermediary step in creating an XML Schema. Each selected PIM Class element is converted to an «XSDcomplexType» element.

#### **Example**

The PIM elements



After transformation become the PSM elements



These in turn generate this XSD

```
<?xml version="1.0" encoding="ISO-8859-1"?>
```

- <xs:schema xmlns:xs="http://www.w3.org/2001/XMLSchema">
- <xs:element name="Account" type="Account"/>
- <xs:complexType name="Account">
- <xs:sequence>
- <xs:element name="name" type="xs:string"/>
- <xs:element name="billingAddress" type="xs:string"/>
- <xs:element name="emailAddress" type="xs:string"/>
- <xs:element name="closed" type="xs:boolean"/>
- <xs:element name="deliveryAddress" type="xs:string"/>
- <xs:element ref="Order"/>
- <xs:element ref="ShoppingBasket"/>
- </xs:sequence>
- </xs:complexType>
- <xs:element name="LineItem" type="LineItem"/>
- <xs:complexType name="LineItem">
- <xs:sequence>
- <xs:element name="quantity" type="xs:integer"/>

```
<xs:element ref="StockItem"/>
</xs:sequence>
</xs:complexType>
<xs:element name="Order" type="Order"/>
<xs:complexType name="Order">
<xs:sequence>
<xs:element name="date" type="xs:date"/>
<xs:element name="deliveryInstructions" type="xs:string"/>
<xs:element name="orderNumber" type="xs:string"/>
<xs:element ref="LineItem"/>
<xs:element name="status" type="OrderStatus"/>
</xs:sequence>
</xs:complexType>
<xs:simpleType name="OrderStatus">
<xs:restriction base="xs:string">
<xs:enumeration value="new"/>
<xs:enumeration value="packed"/>
<xs:enumeration value="dispatched"/>
<xs:enumeration value="delivered"/>
<xs:enumeration value="closed"/>
</xs:restriction>
</xs:simpleType>
<xs:element name="ShoppingBasket" type="ShoppingBasket"/>
<xs:complexType name="ShoppingBasket">
<xs:sequence>
<xs:element ref="LineItem"/>
</xs:sequence>
</xs:complexType>
<xs:element name="StockItem" type="StockItem"/>
<xs:complexType name="StockItem">
<xs:sequence>
<xs:element name="catalogNumber" type="xs:string"/>
</xs:sequence>
</xs:complexType>
<xs:element name="Transaction" type="Transaction"/>
<xs:complexType name="Transaction">
<xs:sequence>
<xs:element name="date" type="xs:date"/>
<xs:element name="orderNumber" type="xs:string"/>
<xs:element ref="Account"/>
<xs:element ref="LineItem"/>
</xs:sequence>
```

</r></rs:complexType>

</xs:schema>

## **Edit Transformation Templates**

A single transformation applies a number of transformation templates, each of which defines a type of object that is acted on within the transformation, and the actions that are performed on objects of that type. The system provides a range of built-in default templates, and each type of transformation uses a specific subset of these templates. Typically, the transformation type and the subset of templates are tailored to the target language. Some default templates within a set have no content; these are 'latent', and represent the potential for acting on an object that is not generally included in the transformation but is perfectly valid if you wanted to include it. An example of a latent template is the Linked Class Base template in the C# transformation.

You can tailor the transformation templates in various ways, including:

- Adjust the code in one or more of the templates in a default set
- Add code to a 'latent' default template
- Add a new custom template, based on one of the defaults but serving a different purpose that you define
- Add a new transformation type containing initially a basic set of default templates
- Add (or remove) a stereotyped override for a template

A stereotyped override directs the transformation to use the modified template only if the element and/or feature are of the specified stereotyped types. If the object or feature are not of that type, the transformation applies the base template.

#### **Access**

Ribbon	Design > Package > Transform > Transform Templates
Keyboard Shortcuts	Ctrl+Alt+H

### **Edit Transformation Templates**

Option	Action
Language	Click on the drop-down arrow and select the name of the transformation.
New Transformation Type	Click on this button if you want to create a new transformation.
	A prompt displays for the name of the transformation; type in the name and click on the OK button.
	The 'Templates' list shows the default set of built-in templates, from which you can develop your transformation. Your custom transformation is not saved or available for use unless you add and/or edit one or more templates in the transformation.
Templates	Lists the transformation templates for the current transformation.  Click on a template name to highlight it and display its content in the Template panel. The 'Modified' column indicates whether you have edited the template for this transformation.
Template	Displays the contents of the currently-selected template, and provides the editor facilities for modifying the template (right-click on the code text).

Stereotype Overrides	Lists the stereotyped templates, for the active base template.
	The 'Modified' column indicates whether you have modified a stereotyped template.
Add New Custom Template	Click on this button to create a custom template to add to the current transformation.
	A dialog displays, prompting you to specify:
	<ul> <li>The object type (base template type) that this new template will respond to - click on the drop-down arrow and select the name (custom template types are not included in this list)</li> </ul>
	The name of the new template - type in the appropriate text
	Click on the OK button. The new template name is added to the list of templates, and it is opened in the template editor ready for you to add its code.
Add New Stereotyped Override	Click on this button to add a new stereotype override for the currently selected template. A dialog displays, prompting you to specify the:
	Base Class (stereotyped Class type - click on the drop-down arrow and click on the type in the list) and/or
	• Feature (click on the drop-down arrow and click on the stereotyped feature in the list)
	Click on the OK button. The override is added to the 'Stereotype Overrides' list.
Get Default Template	Click on this button to update the editor display with the default version of the current built-in template or to clear the content of the current custom template.
	If you have saved the changed template, re-instating the default version is a change, so the 'Modified' field still displays the word 'Yes'.
Save	Click on this button to save the new or edited current template. You cannot switch to another template without saving the current template, so this effectively saves the transition as well.
Delete	Click on this button to delete the current custom template or stereotype override, or the most recent changes to a built-in template (effectively returning it to the default, base content). You cannot delete a built-in template.
	You are prompted to confirm the deletion.
Help	Click on this button to display this Help topic.

### **Notes**

• Transformation template editing is based very strongly on code generation template editing; for additional information on editing transformation templates see the *Code Template Editor* section and the *Editing Source Code* topic

## **Write Transformations**

Enterprise Architect provides a facility to create your own transformations; this can be useful to automate the process of generating more specific models from more general ones, reusing the transformation and preventing errors from being introduced as they might if the models were created by hand. The existing templates will provide a useful guide and reference to assist you when creating new templates.

Transformation templates are based on the Code Generation Template Framework, and an understanding of the way these templates work is critical to be able to adjust existing transformation templates or to create new ones. Therefore it is suggested that you read and understand the topics discussing Code Generation Templates prior to using the Transformation Template language.

#### **Access**

Ribbon	Design > Package > Transform > Transform Templates
Keyboard Shortcuts	Ctrl+Alt+H

## **Factors concerning Transformation Templates**

Factor	Detail
Default Transformation Templates	Enterprise Architect provides a set of default transformation templates that you can use 'as is' or customize to your requirements.
General Syntax for the Intermediary Language	Transformations in Enterprise Architect generate an intermediary code form of the model being created in the transformation. You can review and edit this code.
Intermediary Language Debugging	You can also debug transformation scripts by checking the intermediary code generated from the Transform script.
Editing transformation templates and code	When writing transformations, you use the facilities of the common Code Editor.
Code Template Framework	You use the Code Template Framework to perform forward engineering of UML models. The Transformation Template Framework is derived from this.
Syntax for Creating Objects	To generate objects or elements in a transformation, you apply a specific syntax in the template script.
Syntax for Creating Connectors	To generate connectors (relationships) in a transformation, you also apply a specific syntax in the template script.
Transforming Duplicate Information	In many transformations there is a substantial amount of information to be copied. Rather than place this information in the template, you can use macros to read it from its source.
Transforming Template	In a transformation template, if you are transforming Template Binding connector

Parameter Substitutions	binding parameter substitutions, you can use the Template Parameter substitution macros.	
Converting Types	You can apply various methods for converting data types to different target platform types.	
Converting Names	You can apply various methods for converting names of elements to different target platform naming conventions.	
Cross References	During a transformation, you can perform cross verification of transformed elements.	

### **Notes**

- Further hints and tips can be gleaned from a close study of the Transformation Templates provided with Enterprise Architect
- The Transformation Template editor applies the facilities of the common Code Editor

# **Default Transformation Templates**

Transformation templates provide the ability to represent the existing information in a model in a modified way. When creating a new transformation Enterprise Architect provides a default set of transformation templates that perform a direct copy of the source model to the target model. This allows you to think in terms of how the source model and target model are different. For each template you are able to prevent properties from being copied and add additional information until the appropriate target model is created.

You can list and examine the default templates in the Transformation Editor. The combination of default templates varies according to the language you are transforming.

#### **Access**

Ribbon	Design > Package > Transform > Transform Templates
Keyboard Shortcuts	Ctrl+Alt+H

#### **Notes**

 When creating a new transformation you must modify at least one template before the new transformation becomes available

# **Intermediary Language**

All transformations in Enterprise Architect create an intermediary language form of the model to generate. You can access and edit the file containing this intermediary language code using an external editor. Each object is represented in this language by the object type (for example, Class, Action, Method, Generalization or Tag) followed by the object properties and the features that it is made from; the grammar of the object description resembles this:

```
element:
    elementName { (elementProperty | element)* }
elementProperty:
    packageName
    stereotype
    propertyName = " propertyValueSymbol* "
packageName:
    name = " propertyValueSymbol* " (. " propertyValueSymbol* ")*
stereotype:
    stereotype = " propertyValueSymbol* " (, " propertyValueSymbol* ")*
propertyValueSymbol:
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
    \\
```

- elementName is any one of the set of element types
- propertyName is any one of the set of properties

Literal strings can be included in property values by 'escaping' a quote character:

```
default = "\"Some string value.\""
```

# **Intermediary Language Debugging**

The script from an MDA template produces intermediate language text. However, on generating the model this script could return errors. When an error occurs, you can view and debug the generated text externally, preferably in an editor that prompts on updates to the file alterations.

#### **Access**

Ribbon	Design > Package > Transform > Transform Selection	
Keyboard Shortcuts	Ctrl+H Ctrl+Shift+H	(transform selected elements) (transform current Package)

## Debug when errors are returned on generating altered code

Step	Description
1	Select the Package to be transformed, and the 'Transform Package' option.  The 'Model Transformations' dialog displays.
2	In the 'Name' column, select the checkbox against the type of transformation being altered.
3	In the 'Intermediary File' field, click on the button and set the file location into which to generate the code.
4	Select the 'Write Always' checkbox, and click on the Write Now button to generate the script.  This only generates the script, not the model.
5	If an error is returned specifying the line number of the problem, open the file in an external Code Editor (with Line Numbering) and locate the line number of problem.
6	Alter the template code to correct the error.
7	Click on the Do Transform button to check that the alteration has corrected the problem.

### **Example**

```
For a MySQL database, the template code might resemble this: $enumFieldName = "test"

Column
```

```
name= %qt%% CONVERT_NAME ($enumFieldName, "Pascal Case", "Camel Case")%%qt%
type= %qt%% CONVERT_TYPE (genOptDefaultDatabase, "Enum")%%qt%
}
This returns the output in the generated text file as:
Column
{
name = "test"
type = "ENUM"
}
```

If there is an error in the original transform, such as a spelling error - 'Colum' - clicking the Do Transform button returns an error message referring to the first line of intermediate code that includes the error 'Colum'.

# **Objects**

```
Objects are generated in a transformation as text in this form:
```

```
objectType
      objectProperties*
     XRef{xref}*
      Tag{tag}*
      Attribute {attributes}*
      Operation {operations}*
      Classifier{classifiers}*
      Parameter {parameters}*
   }
For example:
  Class
   {
      name = "Example"
      language = "C++"
      Tag
         name = "defaultCollectionClass"
         value = "List"
      }
      Attribute
         name = "count"
         type = "int"
      }
   }
```

Every object created in a transformation should include an XRef syntax element (see the end of this topic), as it helps the system to synchronize with the object and makes it possible to create a connector to that Class in the transformation.

## Syntax elements in the code

Element	Detail
objectType	objectType is one of these: • Action
	ActionPin
	Activity

- ActivityParameter
- ActivityPartition
- ActivityRegion
- Actor
- Association
- Change
- Class
- Collaboration
- CollaborationUse
- Component
- DeploymentSpecification
- DiagramFrame
- Decision
- EntryPoint
- Event
- ExceptionHandler
- ExecutionEnvironment
- ExitPoint
- ExpansionNode
- ExpansionRegion
- ExposedInterface
- GUIElement
- InteractionFragment
- InteractionOccurrence
- InteractionState
- Interface
- InterruptibleActivityRegion
- Issue
- Iteration
- Object
- ObjectNode
- MergeNode
- MessageEndpoint
- Node
- Package
- Parameter
- Part
- Port
- ProvidedInterface
- RequiredInterface
- Requirement
- Sequence
- State
- StateMachine

	StateNode
	Synchronization
	• Table
	TimeLine
	• Trigger
	• UMLDiagram
	• UseCase
objectProperties	objectProperties is zero, or one instance of one or more of these:
J I	• Abstract
	• Alias
	• Arguments
	• Author
	• Cardinality
	• Classifier
	• Complexity
	• Concurrency
	• Filename
	Header
	<ul><li>Import</li><li>IsActive</li></ul>
	• IsLeaf
	• IsRoot
	IsSpecification
	Keyword
	• Language
	Multiplicity
	• Name
	• Notes
	• ntype
	• Persistence
	• Phase
	• Scope
	• Status
	• Stereotype
	• Version
	Visibility
Attribute	Attribute has the same structure as objectType, and includes these properties:
	• Alias
	• Classifier
	• Collection
	• Container
	Containment
	• Constant
	Companie

	D.C. I
	• Default
	• Derived
	• LowerBound
	• Name
	• Notes
	Ordered
	• Scope
	• Static
	• Stereotype
	• Type
	UpperBound
	• Volatile
	Attribute also includes these elements:
	Classifier
	• Tag
	• XRef
Operation	Operation has the same structure as objectType, and includes these properties:
operation	Abstract
	• Alias
	Behavior
	• Classifier
	• Code
	• Constant
	• IsQuery
	• Name
	• Notes
	• Pure
	<ul><li>ReturnArray</li><li>Scone</li></ul>
	• Stereotype
	• Type
	Operation also includes these elements:
	• Classifier
	• Parameter
	• Tag
	• XRef
Parameter	Parameter has the same structure as objectType, and includes the Tag element and these properties:
	• Classifier
	Default

	<ul> <li>Fixed</li> <li>Name</li> <li>Notes</li> <li>Kind</li> <li>Stereotype</li> </ul>
Tag	Tag has these properties:  Name Value

## **Special Cases**

Certain types of object have variations of the object definition syntax.

Object	Detail
Packages	Packages differ from other objects in these ways:
	<ul> <li>They have a reduced set of properties: alias, author, name, namespaceRoot, notes, scope, stereotype and version</li> </ul>
	The property namespaceRoot is only given to Packages
	A name must be specified for each Package
	<ul> <li>The name property can be a qualified name; when a qualified name is specified, the properties given are applied only to the final Package</li> </ul>
	Only Packages can contain other Packages
	Packages cannot contain attributes and operations
XRef	Cross references are defined using the transform statements. The properties include:  • Namespace
	• Name
	• Source
	• Notes
Tables	Tables are a special type of object, with these differences from other object types:
	They can include columns and primary keys
	They cannot include attributes
Columns	Columns are similar to attributes, but have an autonumber element containing Startnum and its increment, and these added properties:
	• Length
	• NotNull
	• Precision
	• PrimaryKey
	• Scale
	Unique
	In the column definition, you cannot assign a value to the NotNull, PrimaryKey or Unique properties.

## **Connectors**

The process of creating connectors in a transformation has the same form as for creating elements (objects). It is a little more complex, because you also define each end of the connector - the source and target.

Connectors are represented in the Intermediary language as:

```
ConnectorType
     connectorProperties*
     AssociationClass {associationClassProperties*}
     Source {sourceProperties*}
     Target {targetProperties*}
   }
For example:
   Association
     name="anAssociation"
     stereotype=""
     direction="Unspecified"
      Source
         access="Private"
         navigability="Unspecified"
     Target
         access="Private"
         multiplicity="1..*"
   }
```

### Syntax elements in the code

Element	Detail
ConnectorType	ConnectorType is one of these:
	Abstraction
	Aggregation
	Assembly
	Association
	Collaboration
	ControlFlow

Delegate Dependency Deployment ForeignKey Generalization InformationFlow Instantiation Interface InterruptFlow Manifest Nesting NoteLink ObjectFlow Package Realization Sequence Substitution TemplateBinding Transition Usage Usecase Uses  connectorProperties  connectorProperties  connectorProperties  connectorProperties  connectorProperties  connectorProperties  connectorProperties are one instance of these: associationClassProperties  associatiorClassProperties  associationClassProperties  associationClassProperties are one instance of these: Classifier XRef		• Composton
Dependency Deployment ForeignKey Generalization InformationFlow Instantiation Interface Interface InterraptFlow Manifest Nesting NoteLink ObjectFlow Package Realization Sequence Substitution TemplateBinding Transition Usage Usecuse Uses  connectorProperties  connectorProperties  connectorProperties  alias direction notes name stereotype tag XRef  associationClassProperties  associationClassProperties  associationClassProperties  cornecion on or more of these: Classifier XRef  sourceProperties  association on or more of these: accuse on or		• Connector
Deployment ForcignKey Generalization Instantiation Interrace InterruptFlow Manifest Nesting NoteLink ObjectFlow Package Realization Sequence Substitution Transition Usage UseCase UseS  connectorProperties  connectorProperties  connectorProperties  connectorProperties are one instance of these: alias direction notes name stereotype tag XRef  associationClassProperties  sourceProperties  concerproperties  associationClassProperties  associationClassProperties  associationClassProperties  associationClassProperties  associationClassProperties  associationClassProperties  associationClassProperties  associationClassProperties are one instance of these: Classifier XRef  sourceProperties  associationClassProperties are each a reference to an element and zero, or one instance of one or more of these: aggregation alias allowduplicates changeable constraint		
ForeignKey Generalization InformationFlow InformationFlow Interrace InterruptFlow Manifest Nesting NoteLink ObjectFlow Package Realization Sequence Substitution TemplateBinding Transition Usage UseCase Uses ConnectorProperties  connectorProperties  connectorProperties  connectorProperties  connectorProperties  connectorProperties  connectorProperties  connectorProperties  connectorProperties is zero, or one instance of one or more of these: alias direction notes name stereotype tag XRef  associationClassProperties  associationClassProperties are one instance of these: Classifier XRef  sourceProperties  sourceProperties  sourceProperties  associationClassProperties are one instance of these: classifier XRef  sourceProperties  sourceProperties  alias allowduplicates changeable constraint		
Generalization InformationFlow Instantiation Interface InterruptFlow Manifest Nesting NoteLink ObjectFlow Package Realization Sequence Substitution TemplateBinding Transition Usage UseCase Uses Uses  connectorProperties  connectorProperties  alias direction notes name stereotype 1ag XRef  associationClassProperties  associationClassProperties  sourceProperties  sourceProperties  sourceProperties  connectorProperties  associationClassProperties  associationClassProperties		
InformationFlow Instantiation Interface InterruptFlow Mamilest Nesting NoteLink ObjectFlow Package Realization Sequence Substitution TemplateBinding Transition Usage UseCase Uses  connectorProperties  connectorProperties  connectorProperties is zero, or one instance of one or more of these: alias direction notes name stereotype tag XRef  associationClassProperties  associationClassProperties  associationClassProperties  associationClassProperties  associationClassProperties  associationClassProperties associationClassProperties are one instance of these: Classifier XRef  sourceProperties  associationClassProperties are one instance of these: associationClassProperties associationClassProperties are one instance of these: classifier associationClassProperties are each a reference to an element and zero, or one instance of one or more of these: aggregation alias allowduplicates changeable constraint		
Instantiation Interface InterruptFlow Manifest Nesting NoteLink ObjectFlow Package Realization Sequence Substitution TemplateBinding Transition Usage UseCase Uses  connectorProperties  connectorProperties  connectorProperties  connectorProperties acre one instance of one or more of these: alias direction notes name stereotype tag XRef  associationClassProperties  associationClassProperties  conceProperties  sourceProperties  sourceProperties  sourceProperties  associationClassProperties are one instance of these: Classifier XRef  sourceProperties  allowduplicates changeable constraint		
Interrace InterruptFlow Manifest Nesting NoteLink ObjectFlow Package Realization Sequence Substitution TemplateBinding Transition Usage UseCase Uses  connectorProperties  connectorProperties  connectorProperties  connectorProperties are one instance of one or more of these: alias direction notes name stereotype tag XRef  associationClassProperties  associationClassProperties  sourceProperties  sourceProperties  sourceProperties  sourceProperties  sourceProperties and targetProperties are each a reference to an element and zero or one instance of one or more of these: aggregation alias allowduplicates changeable constraint		
InterruptFlow Manifest Nesting NoteLink ObjectFlow Package Realization Sequence Substitution Transition Usage UseCase Uses  connectorProperties  connectorProperties  connectorProperties  connectorProperties  associationClassProperties  associationClassProperties  associationClassProperties  associationClassProperties  associationClassProperties  associationClassProperties  associationClassProperties  associationClassProperties  associationClassProperties associationClassProperties are one instance of these: Classifier XRef  sourceProperties  associationClassProperties are each a reference to an element and zero, or one instance of one or more of these: aggregation alias allowduplicates changeable constraint		
Manifest     Nesting     NoteLink     ObjectFlow     Package     Realization     Sequence     Substitution     TemplateBinding     Transition     Usage     UseCase     Uses  connectorProperties  connectorProperties  connectorProperties is zero, or one instance of one or more of these:     alias     direction     notes     name     stereotype     tag     XRef  associationClassProperties  associationClassProperties  courceProperties  sourceProperties  sourceProperties  associationClassProperties are one instance of these:     classifier     XRef  sourceProperties  associationClassProperties are each a reference to an element and zero, or one instance of one or more of these:     aggregation     alias     allowduplicates     changeable     constraint		Interface
Nesting     NoteLink     ObjectFlow     Package     Realization     Sequence     Substitution     TemplateBinding     Transition     Usage     UseCase     UseS  connectorProperties  connectorProperties is zero, or one instance of one or more of these:     alias     direction     notes     name     stereotype     tag     XRef  associationClassProperties  associationClassProperties  courceProperties  associationClassProperties  associationClassProperties are one instance of these:     classifier     XRef  sourceProperties  associationClassProperties are each a reference to an element and zero, or one instance of one or more of these:     classifier     xRef  sourceProperties  associationClassProperties and targetProperties are each a reference to an element and zero, or one instance of one or more of these:     aggregation     alias     allowduplicates     changeable     constraint		InterruptFlow
NoteLink ObjectFlow Package Realization Sequence Substitution TemplateBinding Transition Usage UseCase Uses ConnectorProperties  connectorProperties  connectorProperties is zero, or one instance of one or more of these: alias direction notes name stereotype tag XRef  associationClassProperties  associationClassProperties  sourceProperties  sourceProperties  sourceProperties  sourceProperties  associationClassProperties associationClassProperties are one instance of these: Classifier XRef  sourceProperties aggregation alias allowduplicates changeable constraint		Manifest
ObjectFlow     Package     Realization     Sequence     Substitution     TemplateBinding     Transition     Usage     UseCase     Uses  connectorProperties  connectorProperties is zero, or one instance of one or more of these:     alias     direction     notes     name     stereotype     tag     XRef  associationClassProperties  associationClassProperties  courceProperties are one instance of these:     Classifier     XRef  sourceProperties  sourceProperties  associationClassProperties are each a reference to an element and zero, or one instance of one or more of these:     aggregation     alias     allowduplicates     changeable     constraint		Nesting
Package Realization Sequence Substitution TemplateBinding Transition Usage UseCase Uses  connectorProperties  connectorProperties  connectorProperties is zero, or one instance of one or more of these: alias direction notes name stereotype tag XRef  associationClassProperties  consciationClassProperties  associationClassProperties are one instance of these: Classifier XRef  sourceProperties  sourceProperties  associationClassProperties are each a reference to an element and zero, or one instance of one or more of these: aggregation alias allowduplicates changeable constraint		NoteLink
Realization Sequence Substitution TemplateBinding Transition Usage UseCase Uses  connectorProperties  connectorProperties  connectorProperties is zero, or one instance of one or more of these: alias direction notes name stereotype tag XRef  associationClassProperties  associationClassProperties  constraint  sourceProperties  associationClassProperties are one instance of these: classifier XRef  sourceProperties aggregation alias allowduplicates changeable constraint		ObjectFlow
Realization Sequence Substitution TemplateBinding Transition Usage UseCase Uses  connectorProperties  connectorProperties  connectorProperties is zero, or one instance of one or more of these: alias direction notes name stereotype tag XRef  associationClassProperties  associationClassProperties  constraint  sourceProperties  associationClassProperties are one instance of these: classifier XRef  sourceProperties aggregation alias allowduplicates changeable constraint		Package
Sequence Substitution TemplateBinding Transition Usage UseCase Uses  connectorProperties  connectorProperties  connectorProperties is zero, or one instance of one or more of these: alias direction notes name stereotype tag XRef  associationClassProperties  associationClassProperties  conceProperties are one instance of these: Classifier XRef  sourceProperties targetProperties  associationClassProperties and targetProperties are each a reference to an element and zero or one instance of one or more of these: aggregation alias allowduplicates changeable constraint		
Substitution     TemplateBinding     Transition     Usage     UseCase     Uses  connectorProperties  connectorProperties is zero, or one instance of one or more of these:     alias     direction     notes     name     stereotype     tag     XRef  associationClassProperties  associationClassProperties are one instance of these:     Classifier     XRef  sourceProperties  sourceProperties  association ClassProperties are each a reference to an element and zero or one instance of one or more of these:     aggregation     alias     allowduplicates     changeable     constraint		
TemplateBinding     Transition     Usage     UseCase     Uses   connectorProperties  connectorProperties is zero, or one instance of one or more of these:     alias     direction     notes     name     stereotype     tag     XRef  associationClassProperties  associationClassProperties  consistinct  associationClassProperties  associationClassProperties are one instance of these:     Classifier     XRef  sourceProperties  associationClassProperties are each a reference to an element and zero or one instance of one or more of these:     aggregation     alias     allowduplicates     changeable     constraint		_
Transition     Usage     UseCase     Uses   connectorProperties  connectorProperties is zero, or one instance of one or more of these:     alias     direction     notes     name     stereotype     tag     XRef  associationClassProperties  connectorProperties are one instance of these:     Classifier     XRef  sourceProperties  sourceProperties  targetProperties  association ClassProperties are each a reference to an element and zero or one instance of one or more of these:     aggregation     alias     allowduplicates     changeable     constraint		
Usage UseCase Uses  connectorProperties  connectorProperties is zero, or one instance of one or more of these: alias direction notes name stereotype tag XRef  associationClassProperties  associationClassProperties are one instance of these: Classifier XRef  sourceProperties targetProperties  sourceProperties are each a reference to an element and zero, or one instance of one or more of these: aggregation alias allowduplicates changeable constraint		
UseCase     Uses  connectorProperties  connectorProperties is zero, or one instance of one or more of these:     alias     direction     notes     name     stereotype     tag     XRef  associationClassProperties  constraint  sourceProperties  constraint		
connectorProperties  connectorProperties is zero, or one instance of one or more of these:  alias direction notes name stereotype tag XRef  associationClassProperties associationClassProperties are one instance of these: Classifier XRef  sourceProperties targetProperties targetProperties  sourceProperties and targetProperties are each a reference to an element and zero or one instance of one or more of these: aggregation alias allowduplicates changeable constraint		
connectorProperties  connectorProperties is zero, or one instance of one or more of these:  alias direction notes name stereotype tag XRef  associationClassProperties  considering associationClassProperties are one instance of these: Classifier XRef  sourceProperties  sourceProperties  con one instance of one or more of these: aggregation alias allowduplicates changeable constraint		
associationClassProperties  associationClassProperties  associationClassProperties are one instance of these:  Classifier  XRef  sourceProperties  targetProperties  sourceProperties  associationClassProperties are each a reference to an element and zero or one instance of one or more of these:  aggregation  alias  allowduplicates  changeable  constraint		
direction     notes     name     stereotype     tag     XRef  associationClassProperties  associationClassProperties are one instance of these:     Classifier     XRef  sourceProperties targetProperties targetProperties  aggregation     alias     allowduplicates     changeable     constraint	connectorProperties	connectorProperties is zero, or one instance of one or more of these:
<ul> <li>notes</li> <li>name</li> <li>stereotype</li> <li>tag</li> <li>XRef</li> </ul> associationClassProperties <ul> <li>associationClassProperties are one instance of these:</li> <li>Classifier</li> <li>XRef</li> </ul> sourceProperties <ul> <li>sourceProperties and targetProperties are each a reference to an element and zero or one instance of one or more of these:</li> <li>aggregation</li> <li>alias</li> <li>allowduplicates</li> <li>changeable</li> <li>constraint</li> </ul>		• alias
<ul> <li>name         <ul> <li>stereotype</li> <li>tag</li> <li>XRef</li> </ul> </li> <li>associationClassProperties         <ul> <li>Classifier</li> <li>XRef</li> </ul> </li> <li>sourceProperties         <ul> <li>targetProperties</li> </ul> </li> <li>sourceProperties and targetProperties are each a reference to an element and zero or one instance of one or more of these:         <ul> <li>aggregation</li> <li>alias</li> <li>allowduplicates</li> <li>changeable</li> <li>constraint</li> </ul> </li> </ul>		• direction
stereotype     tag     XRef  associationClassProperties  associationClassProperties are one instance of these:     Classifier     XRef  sourceProperties  sourceProperties and targetProperties are each a reference to an element and zero, or one instance of one or more of these:     aggregation     alias     allowduplicates     changeable     constraint		• notes
<ul> <li>tag</li> <li>XRef</li> <li>associationClassProperties are one instance of these:         <ul> <li>Classifier</li> <li>XRef</li> </ul> </li> <li>sourceProperties         <ul> <li>targetProperties</li> <li>aggregation</li> <li>alias</li> <li>allowduplicates</li> <li>changeable</li> <li>constraint</li> </ul> </li> </ul>		• name
tag     XRef  associationClassProperties  associationClassProperties are one instance of these:     Classifier     XRef  sourceProperties  sourceProperties and targetProperties are each a reference to an element and zero or one instance of one or more of these:     aggregation     alias     allowduplicates     changeable     constraint		• stereotype
associationClassProperties  associationClassProperties are one instance of these:  Classifier  XRef  sourceProperties  sourceProperties and targetProperties are each a reference to an element and zero, or one instance of one or more of these:  aggregation  alias  allowduplicates  changeable  constraint		
Classifier  XRef  sourceProperties targetProperties  sourceProperties and targetProperties are each a reference to an element and zero, or one instance of one or more of these:  aggregation alias allowduplicates changeable constraint		Title:
sourceProperties targetProperties  sourceProperties and targetProperties are each a reference to an element and zero or one instance of one or more of these:  aggregation alias allowduplicates changeable constraint	associationClassProperties	associationClassProperties are one instance of these:
sourceProperties  targetProperties  sourceProperties and targetProperties are each a reference to an element and zero, or one instance of one or more of these:  aggregation alias allowduplicates changeable constraint		Classifier
targetProperties  or one instance of one or more of these:  aggregation  alias  allowduplicates  changeable  constraint		• XRef
targetProperties  or one instance of one or more of these:  aggregation  alias  allowduplicates  changeable  constraint		
<ul> <li>aggregation</li> <li>alias</li> <li>allowduplicates</li> <li>changeable</li> <li>constraint</li> </ul>		sourceProperties and targetProperties are each a reference to an element and zero,
<ul> <li>alias</li> <li>allowduplicates</li> <li>changeable</li> <li>constraint</li> </ul>	targetProperties	
<ul><li>allowduplicates</li><li>changeable</li><li>constraint</li></ul>		
<ul><li>changeable</li><li>constraint</li></ul>		
• constraint		
• containment		
• navigability		• navigability
a manifest like		<ul><li>constraint</li><li>containment</li></ul>

	<ul> <li>membertype</li> <li>multiplicity</li> <li>Notes</li> <li>ordered</li> <li>qualifier</li> <li>role</li> <li>scope</li> <li>stereotype</li> <li>tag</li> </ul>
Element Reference	An element reference is either a guid that references an element that already exists before the transformation, or an XRef to reference an element that is created by a transformation.  • guid  • XRef

### **Notes**

• Each connector is transformed at both end objects, therefore the connector might appear twice in the transformation; this is not a problem, although you should check carefully that the connector is generated exactly the same way, regardless of which end is on the current Class

## **Transform Connectors**

When you transform a connector, you can use two different types of Class as the connector ends: either a Class created by a transformation, or an existing Class for which you already know the GUID.

### Connect to a Class Created by a Transformation

The most common connection is to a Class created by a transformation; to create this connection you use three items of information:

- The original Class GUID
- The name of the transformation
- The name of the transformed Class

This type of connector is created using the TRANSFORM\_REFERENCE function macro; when the element is in the current transformation, it can be safely omitted from the transformation. The simplest example of this is when you have created multiple Classes from a single Class in a transformation, and you want a connector between them; consider this script from the EJB Entity transformation:

```
Dependency
{
%TRANSFORM_REFERENCE("EJBRealizeHome",classGUID)% stereotype="EJBRealizeHome"
Source
{
%TRANSFORM_REFERENCE("EJBEntityBean",classGUID)%
}
Target
{
%TRANSFORM_REFERENCE("EJBHomeInterface",classGUID)%
}
}
```

In this script there are three uses of the TRANSFORM\_REFERENCE macro: one to identify the connector for synchronization purposes and the other two to identify the ends; all three use the same source GUID, because they all come from the one original Class. None of the three have to specify the transformation because the two references are to something within the current transformation - each of them then only has to identify the transform name.

It is also possible to create a connector from another connector. You can create a connector template and list all connectors connected to a Class from the Class level templates; you don't have to worry about only generating the connector once, because if you have created a TRANSFORM\_REFERENCE for the connector then the system automatically synchronizes them.

This script copies the source connector:

```
%connectorType%
{
%TRANSFORM_CURRENT()%
%TRANSFORM_REFERENCE("Connector",connectorGUID)%
Source
{
%TRANSFORM_REFERENCE("Class",connectorSourceGUID)%
%TRANSFORM_REFERENCE("Class",connectorSourceGUID)%
```

```
Target
{
%TRANSFORM_REFERENCE("Class",connectorDestGUID)%
%TRANSFORM_CURRENT("Target")%
}
}
```

## Connecting to a Class for which you know the GUID

The second type of Class that you can use as a connector end is an existing element for which you know the current GUID. To create this connection, specify the GUID of the target Class in either the source or target end; this script creates a Dependency from a Class created in a transformation, to the Class it was transformed from:

```
Dependency
{
%TRANSFORM_REFERENCE("SourceDependency",classGUID)%
stereotype="transformedFrom"
Source
{
%TRANSFORM_REFERENCE("Class",classGUID)%
}
Target
{
GUID=%qt%%classGUID%%qt%
}
}
```

#### **Notes**

• Each connector is transformed at both end objects, therefore the connector might appear twice in the transformation; this is not a problem, although you should check carefully that the connector is generated exactly the same way, regardless of which end is on the current Class

## **Transform Foreign Keys**

Enterprise Architect supports the transformation into Foreign Keys of many different types of relationship defined between entities in a logical model.

Each Foreign Key in a Physical model is represented by the combination of a stereotyped connector and an operation in each of the involved Tables. Foreign Key transformations are achieved with the 'Connector' template in the DDL language. This template generates an intermediate dataset that is then interpreted by Enterprise Architect's transformation engine to create all the required physical entities and connectors.

By default, Enterprise Architect supports transformations of these connector types:

- Generalization this kind of connector will create a Foreign Key with a multiplicity of 0..1 in the source and 1 in the
  destination
- Association Class this kind of connector will create a 'join' table linking both the source and destination Tables
- Association/Aggregation these kinds of connector use the multiplicity defined in the Logical model's relationship to join the source and destination Tables

All Foreign Key definitions will cause the addition of a new integer (or equivalent) column in both source and destination Tables, which will act as the Primary Key in the source Table and the Foreign Key column in the destination Table. The default names for the new columns will be the Table name with the suffix of 'ID' added, whilst the names of the Foreign Keys will be automatically generated using the FK DDL template.

# **Copy Information**

In many transformations there is a substantial amount of information to be copied.

It would be tedious to type all of the common information into a template so that it is copied to the transformed Class; the alternative is to use the TRANSFORM\_CURRENT and TRANSFORM\_TAGS function macros.

### **Use of Macros**

Objective	Detail
Copy Object	TRANSFORM_CURRENT ( <listofexcludeditems>)</listofexcludeditems>
	The function generates an exact copy of all the properties of the current item, except for the items named in <li>stOfExcludedItems&gt;.</li>
Copy Connector	Another form of the function is available when transforming connectors to copy either end of the connector:
	TRANSFORM_CURRENT ( <connectorend>, <li>dedItems&gt;)</li></connectorend>
	This generates an exact copy of the connector end specified by <connectorend> (either Source or Target) except for the items named in <li>listOfExcludedItems&gt;.</li></connectorend>
Copy Tags	TRANSFORM_TAGS ( <listofexcludeditems>)</listofexcludeditems>
	The function generates an exact copy of all the Tagged Values of the current item, except for the items named in <li>clistOfExcludedItems&gt;.</li>

# **Convert Types**

Different target platforms almost certainly require different data types, so you usually require a method of converting between types. This is offered by the macro:

CONVERT TYPE (<destinationLanguage>, <originalType>)

This function converts <originalType> to the corresponding type in <destinationLanguage> using the datatypes and common types defined in the model, where <originalType> is assumed to be a platform independent common type.

A similar macro is available when transforming common datatypes to the datatypes for a specified database:

CONVERT DB TYPE (<destinationDatabase>, <originalType>)

This function converts <originalType> to the corresponding datatypes in <destinationDatabase>, which is defined in the model; <originalType> refers to a platform independent common datatype.

## **Convert Names**

Different target platforms use different naming conventions, so you might not want to copy the names of your elements directly into the transformed models. To facilitate this requirement, the transformation templates provide a CONVERT NAME function macro.

Another way in which you can transform a name is to remove a prefix from the original name, with the REMOVE PREFIX macro.

### **CONVERT\_NAME** (<originalName>, <originalFormat>, <targetFormat>)

This macro converts <originalName>, which is assumed to be in <originalFormat>, to <targetFormat>.

The supported formats are:

- Camel Case: the first word begins with a lower-case letter but subsequent words start with an upper-case letter; for example, myVariableTable
- Pascal Case: the first letter of each word is upper case; for example, MyVariableTable
- Spaced: words are separated by spaces; the case of letters is ignored
- Underscored: words are separated by underscores; the case of letters is ignored

The original format might also specify a list of delimiters to be used. For example a value of '\_' breaks words whenever either a space or underscore is found. The target format might also use a format string that specifies the case for each word and a delimiter between them. It takes this form:

<firstWord> (<delimiter>) <otherWords>

- <firstWord> controls the case of the first word
- <delimiter> is the string generated between words
- <otherWords> applies to all words after the first word

Both <firstWord> and <otherWords> are a sequence of two characters. The first character represents the case of the first letter of that word, and the second character represents the case of all subsequent letters. An upper case letter forces the output to upper case, a lower case letter forces the output to lower case, and any other character preserves the original case.

Example 1: To capitalize the first letter of each word and separate multiple words with a space:

"Ht()Ht" to output "My Variable Table"

Example 2: To generate the equivalent of Camel Case, but reverse the roles of upper and lower case; that is, all characters are upper case except for the first character of each word after the first word:

"HT()hT" to output "MY vARIABLE tABLE"

## REMOVE PREFIX(<originalName>, <prefixes>)

This macro removes any prefix found in prefixes> from <originalName>. The prefixes are specified in a semi-colon separated list.

The macro is often used in conjunction with the CONVERT\_NAME macro. For example, this code creates a get property name according to the options for Java:

```
$propertyName=%REMOVE_PREFIX(attName,genOptPropertyPrefix)%
%if genOptGenCapitalisedProperties=="T"%
```

\$propertyName=%CONVERT NAME(\$propertyName, "camel case", "pascal case")%

%endIf%

## **Notes**

• Acronyms are not supported when converting from Camel Case or Pascal Case

## **Cross References**

Cross References are an important part of transformations. You can use them to:

- Find the transformed Class to synchronize with
- Create connectors between transformed Classes
- Specify a classifier of a type
- Determine where to transform to for future transformations

Each Cross Reference has three different parts:

- A Namespace, corresponding to the transformation that generated the element
- A Name, which is a unique reference to something that can be generated in the transformation, and
- A Source, which is the GUID of the element that this element was created from

When writing the templates for a transformation it is easiest to generate the Cross References using the macro defined for this purpose:

TRANSFORM REFERENCE (<name>, <sourceGuid>, <namespace>)

The three parameters are optional. The macro generates a reference that resembles this:

XRef{namespace="<namespace>" name="<name>" source="<sourceGuid>"

- If <name> is not specified the macro gets the name of the current template
- If <sourceGUID> is not specified the macro gets the GUID of the current Class
- If <namespace> is not specified the macro gets the name of the current transformation

The only time that a Cross Reference should be specified is when creating a connector to a Class created in a different transformation.

A good example of the use of Cross References is in the DDL transformation provided with Enterprise Architect. In the Class template a Cross Reference is created with the name 'Table'. Then up to two different connectors can be created, each of which must identify the two Classes it connects using Cross References, while having its own unique Cross Reference.

## **Specify Classifiers**

Objects, attributes, operations and parameters can all reference another element in the model as their type. When this type is created from a transformation you must use a cross reference to specify it, using the macro:

TRANSFORM\_CLASSIFIER (<name>, <sourceGuid>, <namespace>)

This macro generates a cross reference within a classifier element, where the parameters are identical to the TRANSFORM REFERENCE macro but the name Classifier is generated instead of XRef.

If the target classifier already exists in the model before the transformation, TRANSFORM\_CLASSIFIER is inappropriate, so instead the GUID can be given directly to a classifier attribute.

If a classifier is specified for any type, it overrides that type.

# **Transform Template Parameter Substitution**

If you want to provide access in a transformation template to data concerning the transformation of a Template Binding connector's binding parameter substitution in the model, you can use the Template Parameter substitution macros.

### **Factors in the Transformation**

Factor	Detail
Intermediary Language	Template Parameter Substitutions are represented in the Intermediary language as:  TemplateParameterSubstitution  {     Formal { FormalProperties }     Actual { ActualProperties } }  For example:     TemplateParameterSubstitution  {         rormal         {             name=%qt%%parameterSubstitutionFormal%%qt%         }         Actual         {             name=%qt%%parameterSubstitutionActual%%qt%             %TRANSFORM_CLASSIFIER("Class", parameterSubstitutionActualClassifier)%         }     } }
Formal Properties or Actual Properties	FormalProperties and ActualProperties are zero, or one instance of one of these properties:  • name • classifier
Transform of Parameter Substitution Actual parameter	If the Actual parameter is assigned a String Expression, it will transform as Actual name. You can assign the Actual Classifier if you know the GUID:  TemplateParameterSubstitution ( Formal { name=%qt%%parameterSubstitutionFormal%%qt% } Actual

```
name=%qt%%parameterSubstitutionActual%%qt%
classifier=%qt%%parameterSubstitutionActualClassifier%%qt%
If you want the Actual parameter to be transformed so that its Classifier is assigned
with an element that is transformed, then use TRANSFORM CLASSIFIER or
TRANSFORM REFERENCE, as shown:
TemplateParameterSubstitution
Formal
name=%qt%%parameterSubstitutionFormal%%qt%
Actual
name=%qt%%parameterSubstitutionActual%%qt%
%TRANSFORM CLASSIFIER("Class", parameterSubstitutionActualClassifier)%
}
Or
TemplateParameterSubstitution
Formal
name=%qt%%parameterSubstitutionFormal%%qt%
}
Actual
name=%qt%%parameterSubstitutionActual%%qt%
%TRANSFORM_REFERENCE("Class", parameterSubstitutionActualClassifier)%
}
```